

WIZTYPE™
REFERENCE CARD
Commodore 64 Disk Version
by Sydney

LOADING INSTRUCTIONS

1. Turn on power to the drive, the monitor, then the computer.
2. Label side up, insert WIZTYPE™ disk in the disk drive.
3. Close the drive door.
4. When the screen says "Ready," TYPE ◀LOAD"WIZ",8▶, then press ◀RETURN▶.
5. When the screen says "Ready" again, type ◀RUN▶ and press ◀RETURN▶.
6. Make sure the ◀SHIFT LOCK▶ key is off.
7. The computer will ask your name -- up to 50 different people can play WIZTYPE™ and have their statistics recorded before the oldest records will be written over! Enter your name and press ◀RETURN▶.
8. When the banner (title) page appears, press ◀F1▶ to view your choice of lessons.

CONTROL KEYS

- ◀F1▶ To start WIZTYPE™
- ◀F3▶ To begin again at the menu
- ◀F5▶ To turn sound off/on
- ◀F7▶ To pause WIZTYPE™ (press again to continue)

EDITING YOUR OWN FILES

When creating your own lesson or your own drill, you will probably make a few typos – that's OK, nobody's perfect. Use the "INSERT DELETE" key to erase on the line you're currently typing. The "CURSOR" keys let you move up and down to retype other lines. When you're finished creating the lesson, press "SHIFT" and "RETURN" to tell the computer.

You have room for up to 4,000 words in each paragraph lesson, and 250 words in each word drill. The number of files the disk will hold depends on the size of your lessons (there is approximately 100K of extra disk space for your use.)

TO CATALOG YOUR DISK

Once you create your own lessons and your own paragraphs you'll want to use them. If you can't remember their names, catalog your disk before beginning your WIZTYPE™ session. After switching on your computer, type ◀LOAD"\$",8▶ and press ◀RETURN▶. Type ◀LIST▶ and press ◀RETURN▶ again, and everything on the disk will list on the screen. Your "Own Lesson" files are labeled with "###" and your "Paragraph" files with "\$\$\$".

To erase any of your files (to make room for more), input the following lines:

```
◀OPEN 15,8,15▶  
◀PRINT#15,"SO:(filename)▶  
◀CLOSE 15▶
```

You don't need to include the "###" or "\$\$\$" portion of your file name when using WIZTYPE™, but you'll need to include it when you erase a file.

